



Web Zones


Open Chrome (or browser of your choice) and navigate to <http://172.16.10.128/zones> and login with your Windows credentials (computer login).



The image shows a login interface for 'WEB ZONES' powered by 'LIGHTSPEED SYSTEMS'. The interface is displayed on a dark blue background. At the top, the text 'WEB ZONES' is written in a large, white, sans-serif font, with 'POWERED BY LIGHTSPEED SYSTEMS' in a smaller, white, sans-serif font below it. Below the text, there are three white input fields stacked vertically. The first two are empty, and the third contains the text 'LS Apple Open Dir' with a small downward arrow on the right side, indicating a dropdown menu. At the bottom of the interface, there is a dark blue button with the word 'Login' written in white, sans-serif font.




1. Click **Add Web Zone**. This action opens the following page:



2. Enter a meaningful name that students will be able to locate easily from the [Join a Web Zone](#) page, and then click **Save**.

Next we need to setup the web zone

1. From the Web Zones dashboard, click to select the Web Zone to configure, and then click the Rules button.



2. Enter URLs in the Allowed Sites and Blocked Sites lists, and then click Save Rules.
3. URLs (web links) must be in the proper format. **Do not** include "http://" or "https://" in the URL.

Note the option to Block all URLs (except for allow list).

4. Click **Save Rules** at the bottom of the page to apply these settings.
Next we need to add users to the web zone. Students can ask to join a webzone by going to <http://172.16.10.128/joinzone/> and searching for active web zones.

Click Users to view and manage web zone memberships. You must approve requests to join and leave an Open Web Zone.

WEB ZONES
POWERED BY LIGHTSPEED SYSTEMS

Logout

Video Production
Allows some video production articles

about 2 hours
TIME REMAINING

Users Rules

User authentication is turned off.

Join Requests **Members** **Leave Requests**

Accept All Deny All

Melody Page
Location: 69.84.207.62 (69.84.207.62)
Received: less than a minute ago

← DENY ACCEPT →

WEB ZONES
POWERED BY LIGHTSPEED SYSTEMS

Logout

Video Production
Allows some video production articles

about 2 hours
TIME REMAINING

Users Rules

User authentication is turned off.

Join Requests **Members** **Leave Requests**

Deny All Accept All

Melody Page
Location: 69.84.207.62 (69.84.207.62)
Received: less than a minute ago

← DENY ACCEPT →

To remove an individual user from a web zone, click **Release** below the user's name in the Members list.

To remove all users from a web zone, click **Release All** in the top right corner of the Members list.

The screenshot displays the 'Web Zones' interface, powered by Lightspeed Systems. The main header includes a home icon, the 'WEB ZONES' logo, and a 'Logout' link. The current zone is 'Video Production', which allows some video production articles and has a timer set to 'about 2 hours' (TIME REMAINING). Below the header, there are tabs for 'Users' and 'Rules'. A notification states 'User authentication is turned off.' The interface is divided into three columns: 'Join Requests', 'Members', and 'Leave Requests'. The 'Members' column contains a list of users, with the first entry being 'Melody Page'. This entry shows the location as '69.84.207.62 (69.84.207.62)' and the time as 'Entered Zone: less than a minute ago'. A 'RELEASE' button is located below the user entry, and a 'Release All' button is located in the top right corner of the Members list.